Document Number: UM11226

Rev. 2, 06/2019

NXP elQ™ Machine Learning Software Development Environment for i.MX Applications Processors

1. Introduction

Machine Learning (ML) is a computer science domain that has its roots in the 1960s. ML provides algorithms capable of finding patterns and rules in data. ML is a category of algorithm that allows software applications to become more accurate in predicting outcomes without being explicitly programmed. The basic premise of ML is to build algorithms that can receive input data and use statistical analysis to predict an output while updating outputs as new data becomes available.

In 2010, the so-called deep learning started. It is a fast-growing subdomain of ML, based on Neural Networks (NN). Inspired by the human brain, deep learning achieved state-of-the-art results in various tasks; for example, Computer Vision (CV) and Natural Language Processing (NLP). Neural networks are capable of learning complex patterns from millions of examples. A huge adaptation is expected in the embedded world, where NXP is the leader. NXP created eIQ machine learning software for i.MX applications processors, a set of ML tools which allows developing and deploying ML applications on the i.MX 8 family of devices.

Contents

1.	Introduction	1			
2.	NXP eIQ software introduction				
3.	Yocto installation guide				
	3.1. Prerequisites				
	3.2. Building NXP eIQ software support using Yocto				
	Project tools	3			
4.	OpenCV getting started guide	7			
	4.1. OpenCV DNN demos	8			
	4.2. OpenCV standard machine learning demos	15			
5.	Arm Compute Library getting started guide	19			
	5.1. Running DNN with random weight and inputs	19			
	5.2. Running AlexNet using graph API				
6.	TensorFlow getting started guide				
	5.1. Running benchmark application				
7.	TensorFlow Lite getting started guide				
	7.1. Running benchmark application	22			
	7.2. Running image classification example				
8.	Arm NN getting started guide				
	3.1. Running Arm NN tests				
	3.2. Using Arm NN in a custom C/C++ application				
9.	ONNX Runtime getting started guide				
	9.1. Running ONNX Runtime test				
10	References				
	Revision history				



This document provides guidance for the supported ML software for the i.MX family. The document is divided into separate sections, starting with the NXP eIQ introduction, the Yocto installation guide, and the step-by step guide for running all supported DNN and non-DNN examples.

2. NXP eIQ software introduction

The NXP eIO machine learning software development environment provides a set of libraries and development tools for machine learning applications targeted at NXP MCUs and application processors. The NXP eIQ software is concerned only with neural networks inference and standard machine-learning algorithms, leaving neural network training to other specialized software tools and dedicated hardware. The NXP eIQ is continuously expanding to include data-acquisition and curation tools and model conversion for a wide range of NN frameworks and inference engines, such as TensorFlow, TensorFlow Lite, Arm[®] NN, and Arm Compute Library.

The current version of NXP eIQ software of i.MX processors delivers advanced and highly optimized machine learning enablement by providing ML support in Linux OS BSPs for the i.MX 8 family of devices. The NXP eIQ software contains these main Yocto recipes:

- OpenCV 4.0.1
- Arm Compute Library 19.02
- Arm NN 19.02
- ONNX runtime 0.3.0
- TensorFlow 1.12
- TensorFlow Lite 1.12

For more details about the i.MX 8 family of application processors, see the fact sheet [3].

For up-to-date information about NXP machine learning solutions, see the official NXP web page [2] for machine learning and artificial intelligence.




Figure 1. NXP elQ machine learning software

3. Yocto installation guide

This chapter provides a step-by-step guide for configuring and building Linux L4.14.98 GA, the Linux Yocto BSP release for i.MX 8 family of devices [4], with support for NXP eIQ software.

To enable NXP eIQ machine learning software, the main configuration changes are:

- Mandatory: select the right machine learning manifest file (*.xml) see Section 3.2.2, "Yocto project metadata downloading".
- Optional: modify the machine learning configuration file (*.conf) or layer files (*.bb), depending on which special configuration is needed; see Section 3.2.4, "Yocto configuration file modifying" or Section 3.2.5, "OpenCV user build modification".

For more information about the Linux Yocto BSP setup, see the Linux L4.14.98_2.0.0 documentation [5].

3.1. Prerequisites

3.1.1. Hardware requirements

- 1 x Linux OS host machine with a minimum of 120 GB HDD space available and internet connection
- 1 x MCIMX8QM-CPU board with internet connection
- 1 x SDHC card (tested with a 16-GB SDHC Class 10 UHS-I card)
- 1 x MIPI camera MCIMXCAMERA1MP with de-serializer MX8XMIPI4CAM2 for running OpenCV DNN examples using the live camera inputs (optional only)
- LCD HDMI monitor

3.1.2. Software requirements

- 1. Host OS: Ubuntu (tested with 16.04)
- 2. Host packages:
 - The essential Yocto project host packages are:
 - \$: sudo apt-get install gawk wget git-core diffstat unzip texinfo \
 gcc-multilib build-essential chrpath socat libsdl1.2-dev
 - The i.MX layers host packages for the Ubuntu OS host setup are:
 - \$: sudo apt-get install libsdl1.2-dev xterm sed cvs subversion \
 coreutils texi2html docbook-utils python-pysqlite2 help2man gcc \
 g++ make desktop-file-utils libgll-mesa-dev libglul-mesa-dev \
 mercurial autoconf automake groff curl lzop asciidoc u-boot-tools

3.2. Building NXP elQ software support using Yocto Project tools

See the *i.MX Yocto Project User's Guide* document ^[5] or sections 3.2.1 to 3.2.6, and 3.2.9. See the *i.MX Linux User's Guide document* ^[5] or sections 3.2.7 to 3.2.8.

3.2.1. Repo utility installing

This must be done only once.

```
$: mkdir ~/bin
$: curl https://storage.googleapis.com/git-repo-downloads/repo > ~/bin/repo
$: chmod a+x ~/bin/repo
$: PATH=${PATH}:~/bin
```

3.2.2. Yocto project metadata downloading

```
$: mkdir fsl-arm-yocto-bsp
$: cd fsl-arm-yocto-bsp
$: repo init -u https://source.codeaurora.org/external/imx/imx-manifest   -b imx-linux-sumo -m
imx-4.14.98-2.0.0_machinelearning.xml
$: repo sync
```

NOTE

The *imx-4.14.78-1.0.0_machinelearning* manifest file can be also used.

3.2.3. Yocto build setup

```
$: EULA=1 MACHINE=imx8qmmek DISTRO=fsl-imx-xwayland source ./fsl-setup-release.sh -b build-
xwayland
$: echo "BBLAYERS += \" \${BSPDIR}/sources/meta-imx-machinelearning \"" >> conf/bblayers.conf
```

3.2.4. Yocto configuration file modifying

OpenCV 4.0.1 is available to be built and is already installed in the suggested image. Therefore, the *local.conf* file does not have to be modified to include the OpenCV in the Yocto image. However, it is recommended to add some extra packages to this configuration file for a more convenient image. The *local.conf* file is in folder *fsl-arm-yocto-bsp/build-xwayland/conf*.

Add basic development capabilities:

```
EXTRA IMAGE FEATURES = " dev-pkgs debug-tweaks tools-debug tools-sdk ssh-server-openssh"
```

Add packages for networking capabilities:

```
IMAGE_INSTALL_append = " net-tools iputils dhcpcd"
```

Add some generic tools:

```
IMAGE_INSTALL_append = " which gzip python python-pip"
IMAGE_INSTALL_append = " wget cmake gtest git zlib patchelf"
IMAGE_INSTALL_append = " nano grep vim tmux swig tar unzip"
IMAGE INSTALL append = " parted e2fsprogs e2fsprogs-resize2fs"
```

Configure the OpenCV package:

```
IMAGE_INSTALL_append = " opencv python-opencv"
PACKAGECONFIG_remove_pn-opencv_mx8 = "python3"
PACKAGECONFIG_append_pn-opencv_mx8 = " dnn python2 qt5 jasper openmp test neon"
```

Remove the OpenCL support from packages:

```
PACKAGECONFIG_remove_pn-opencv_mx8 = "openc1"
PACKAGECONFIG_remove_pn-arm-compute-library = "openc1"
```

Add CMake for SDK's cross-compile:

```
TOOLCHAIN HOST TASK append = " nativesdk-cmake nativesdk-make"
```

Add packages:

```
IMAGE_INSTALL_append = " arm-compute-library tensorflow tensorflow-lite armnn onnxruntime"
PREFERRED_VERSION_opencv = "4.0.1%"
PREFERRED_VERSION_tensorflow = "1.12.0%"
PREFERRED_VERSION_tensorflow-lite = "1.12.0%"
```

NOTE

OpenCL is currently not supported in the L4.14.98_2.0.0 and L4.14.78_1.0.0 Yocto configurations.

3.2.5. OpenCV user build modification

The OpenCV 4.0.1 is installed with all necessary DNN and ML dependencies in the NXP eIQ software. If some special OpenCV build options are required, add them to the OpenCV recipe file to their separate PACKAGECONFIG section. The *opencv_4.0.1-imx.bb* file is located on the Linux OS host PC in this folder:

fsl-arm-yocto-bsp/sources/meta-imx-machinelearning/recipes-graphics/opency

3.2.6. Image building

The image should be built with Qt 5 support, because some OpenCV examples requires Qt 5 to be enabled in the image:

```
$: bitbake fsl-image-qt5
```

3.2.7. SD card image flashing

The result of the build process is a compressed image which can be found in *tmp/deploy/images/imx8qmmek/fsl-image-qt5-imx8qmmek-<timestamp>.rootfs.sdcard.bz2*, where *<timestamp>* is the image timestamp (for example: 20180509080732).

Decompress the image before flashing it to the SD card:

```
bunzip2 -k -f tmp/deploy/images/imx8qmmek/fsl-image-qt5-imx8qmmek-
<timestamp>.rootfs.sdcard.bz2
```

Flash the SD card (replace "sdX" with the actual SD card device):

```
dd if= tmp/deploy/images/imx8qmmek/fsl-image-qt5-imx8qmmek-<timestamp>.rootfs.sdcard of=/dev/sdX bs=1M && sync
```

NOTE

The Win32DiskImager utility can be also used for the SD card image flashing.

3.2.8. SD card disk space extending

The ML applications require a lot of disk space to store the input model data. By default, the SD card image is created with a small amount of extra space (approximately 500 MB) in the rootfs, which may not be enough for all ML applications.

There are two methods how to extend the SD card free space:

- 1. Define additional free disk space before start the building process. It is done using the IMAGE_ROOTFS_EXTRA_SPACE variable in the *local.conf* file. This step is also described in the Yocto project manual here: https://www.yoctoproject.org/docs/current/mega-manual/mega-manual.html#var-IMAGE_ROOTFS_EXTRA_SPACE.
- 2. Extend the SD card disk space after the image building. This ex-post method is described in more detail in the below section.

Print all SD card partitions of the target board:

```
$: fdisk -1
Device Boot Start End Sectors Size Id Type
/dev/mmcblk1p1 16384 147455 131072 64M c W95 FAT32 (LBA)
/dev/mmcblk1p2 147456 10584063 10436608 5G 83 Linux
```

Start the "fdisk" utility:

```
$: fdisk /dev/mmcblk1
```

Delete the Linux-type partition (second in this case):

```
Command (m for help): d
Partition number (1,2, default 2): 2
Partition 2 has been deleted.
```

Create the new primary partition (second in this case) with the first sector being identical to the original partition:

```
Command (m for help): n
Partition type
    p   primary (1 primary, 0 extended, 3 free)
    e   extended (container for logical partitions)
Select (default p):

Using default response p.
Partition number (2-4, default 2):
First sector (2048-31116287, default 2048): 147456
Last sector, +sectors or +size{K,M,G,T,P} (147456-31116287, default 31116287):
```

Write the new partition and exit the "fdisk" utility:

```
Command (m for help): w
The partition table has been altered.
Syncing disks.
```

Increase the filesystem size of the second partition:

```
$: resize2fs /dev/mmcblk1p2
resize2fs 1.43.8 (1-Jan-2018)
Filesystem at /dev/mmcblk1p2 is mounted on /; on-line resizing required
old_desc_blocks = 1, new_desc_blocks = 1
The filesystem on /dev/mmcblk1p2 is now 3871104 (4k) blocks long.
```

NXP elQ™ Machine Learning Software Development Environment for i.MX Applications Processors, Rev. 2, 06/2019

NOTE

You can also use the "parted" Linux OS command to create a new partition instead of using the "fdisk" command.

Finally, check the free disk space after resizing:

\$: df -h

3.2.9. Generating the Toolchain

The toolchain created by the Yocto Project tools provides a set of tools (compilers, libraries, and header files) to cross-compile the code for the previously-built images. Build the SDK with the Qt 5 support:

```
$: bitbake fsl-image-qt5 -c populate sdk
```

After the build process finishes, it produces an installer script that can be used to install the SDK on the developing system. The script is created in the *tmp/deploy/sdk/fsl-imx-xwayland-glibc-x86_64-fsl-image-qt5-aarch64-toolchain-4.14-sumo.sh*.

4. OpenCV getting started guide

OpenCV is an open-source computer vision library. One of its modules (called ML) provides traditional machine learning algorithms. Another important module in the OpenCV is the DNN, which provides support for neural network algorithms.

OpenCV offers a unitary solution for both the neural network inference (DNN module) and the standard machine learning algorithms (ML module). It includes many computer vision functions, making it easier to build complex machine learning applications in a short amount of time and without being dependent on other libraries.

OpenCV has wide adoption in the computer vision field and is supported by a strong and active community. The key algorithms are specifically optimized for various devices and instructions sets. For i.MX, OpenCV uses the Arm NEON acceleration. The Arm NEON technology is an advanced SIMD (Single Instruction Multiple Data) architecture extension for the Arm Cortex-A series. The Arm NEON technology is intended to improve multimedia user experience by accelerating the audio and video encoding/decoding, user interface, 2D/3D graphics, or gaming. The Arm NEON can also accelerate the signal-processing algorithms and functions to speed up applications such as the audio and video processing, voice and facial recognition, computer vision, and deep learning.

At its core, the OpenCV DNN module implements an inference engine and does not provide any functionalities for neural network training. For more details about the supported models and layers, see the official OpenCV DNN wiki page ^[6].

On the other hand, the OpenCV ML module contains classes and functions for solving machine learning problems such as classification, regression, or clustering. It involves algorithms such as Support Vector Machine (SVM), decision trees, random trees, expectation maximization, k-nearest neighbors, classic Bayes classifier, logistic regression, and boosted trees. For more information, see the official reference manual and machine learning overview. For more details about OpenCV 4.0.1, see the official OpenCV change log web page [7].

4.1. OpenCV DNN demos

After creating a bootable SD card using Yocto, all OpenCV DNN demos are in the /usr/share/OpenCV/samples/bin/ folder (the default demo location). However, the input data, model configurations, and model weights are not located in this folder, because of their size. These files must be downloaded to the device before running the demos:

- Download the *opency_extra.zip* package at this link: github.com/opency/opency_extra/tree/4.0.1
- Unpack the file using unzip opency extra-4.0.1.zip to the SD card root directory < home_dir>.
- Go to the <home_dir>/opencv_extra-4.0.1/testdata/dnn/ folder and run python download_models.py. The script downloads the NN models, configuration files, and input images for some OpenCV examples. This operation may take a while. Copy these dependencies to the /usr/share/OpenCV/samples/bin folder (see also the demo dependencies parts of sections 4.1.x in this document).
- Download the configuration model file at this link:
 <u>github.com/opencv/opencv/blob/master/samples/dnn/models.yml</u>
 The *model.yml* file contains the pre-processing parameters for some DNN examples, which accept the "-zoo" parameter. Copy the model file to the /usr/share/OpenCV/samples/bin folder.

4.1.1. Image classification example

This demo performs image classification using a pre-trained SqueezeNet network.

Demo dependencies (taken from the "opency_extra" package):

- dog416.png
- squeezenet_v1.1.caffemodel
- squeezenet_v1.1.prototxt

Other demo dependencies:

- classification classes ILSVRC2012.txt from /usr/share/OpenCV/samples/data/dnn
- models.yml from github

Running the C++ example with the image input from the default location:

\$: ./example dnn classification --input=dog416.png --zoo=models.yml squeezenet




Figure 2. Image classification graphics output

Running the C++ example with the live camera input from the default location:

\$: ./example dnn classification --zoo=models.yml squeezenet

4.1.2. YOLO object detection example

This demo performs the object detection using the You Only Look Once (YOLO) detector (arxiv.org/abs/1612.08242). It detects objects in a camera/video/image.

For more information about this demo, see the "Loading Caffe framework models" OpenCV tutorial: docs.opencv.org/4.0.1/da/d9d/tutorial dnn yolo.html.

Demo dependencies (taken from the "opency_extra" package):

- dog416.png
- yolov3.weights
- yolov3.cfg

Other demo dependencies:

- models.yml
- object_detection_classes_yolov3.txt from /usr/share/OpenCV/samples/data/dnn

Running the C++ example with the image input from the default location:

\$: ./example dnn object detection -width=1024 -height=1024 -scale=0.00392 -input=dog416.png rgb -zoo=models.yml yolo




Figure 3. YOLO object detection graphics output

Running the C++ example with the live camera input from the default location:

\$: ./example dnn object detection -width=1024 -height=1024 -scale=0.00392 -rgb zoo=models.yml yolo

NOTE

Running this example with the live camera input is very slow, because this example runs only on the CPU.

4.1.3. Image segmentation example

The image segmentation means dividing the image into groups of pixels based on some criteria. You can do this grouping based on color, texture, or some other criteria that you choose.

Demo dependencies (taken from the "opency_extra" package):

- dog416.png
- fcn8s-heavy-pascal.caffemodel
- fcn8s-heavy-pascal.prototxt

Other demo dependencies:

• models.yml

Running the C++ example with the image input from the default location:

\$: ./example dnn segmentation --width=500 --height=500 --rgb --mean=1 --input=dog416.png -zoo=models.yml fcn8s




Figure 4. Image segmentation graphics output

Running the C++ example with the live camera input from the default location:

```
$: ./example dnn segmentation --width=500 --height=500 --rgb --mean=1 --zoo=models.yml fcn8s
```

NOTE

Running this example with the live camera input is very slow, because this example runs only on the CPU.

4.1.4. Image colorization example

This example demonstrates the recoloring of grayscale images using DNN. The demo supports input images only, not the live camera input.

Demo dependencies (taken from the "opency_extra" package):

- colorization_release_v2.caffemodel
- colorization_deploy_v2.prototxt

Other demo dependencies:

basketball1.png

Running the C++ example with the image input from the default location:

\$: ./example_dnn_colorization --model=colorization_release_v2.caffemodel --proto=colorization_deploy_v2.prototxt --image=../data/basketball1.png





Figure 5. Image colorization demo graphics output

4.1.5. Human pose estimation example

This application demonstrates the human or hand pose detection with a pretrained OpenPose DNN. The demo supports only input images, not the live camera input.

Demo dependencies (taken from the "opencv_extra" package):

- grace_hopper_227.png
- openpose_pose_coco.caffemodel
- openpose_pose_coco.prototxt

Running the C++ example with the image input from the default location:

\$: ./example_dnn_openpose --model=openpose_pose_coco.caffemodel -proto=openpose_pose_coco.prototxt --image=grace_hopper_227.png --width=227 --height=227



Figure 6. Human pose estimation graphics output

4.1.6. Object detection example

This demo performs object detection using SqueezeDet. The demo supports only input images, not the live camera input.

Demo dependencies:

- Download the model definition and model weight files from: github.com/kvmanohar22/caffe/tree/obj_detect_loss/proto
- SqueezeDet.caffemodel
- SqueezeDet_deploy.prototxt
- Download the input image from: <u>github.com/opencv/opencv_contrib/blob/4.0.1/modules/dnn_objdetect/tutorials/images/aeroplane_ipg</u>

Running the C++ example with the image input from the default location:

```
$: ./example_dnn_objdetect_obj_detect SqueezeDet_deploy.prototxt SqueezeDet.caffemodel
aeroplane.jpg
```

Running the model on the *aeroplane.jpg* image produces the following text results in the console:

Class: aeroplane Probability: 0.845181 Co-ordinates: 41 116 415 254



Figure 7. Object detection graphics output

4.1.7. CNN image classification example

This demo performs image classification using a pre-trained SqueezeNet network. The demo supports only input images, not the live camera input.

Demo dependencies (taken from the "opency_extra" package):

space_shuttle.jpg

Other demo dependencies:

- Download the *SqueezeNet.caffemodel* model weight file from: github.com/kvmanohar22/caffe/tree/obj_detect_loss/proto
- Download the SqueezeNet_deploy.prototxt model definition file from: github.com/opencv/opencv_contrib/tree/4.0.1/modules/dnn_objdetect/samples/data

Running the C++ example with the image input from the default location:

```
$: ./example_dnn_objdetect_image_classification SqueezeNet_deploy.prototxt
SqueezeNet.caffemodel space shuttle.jpg
```

Running the model on the *space_shuttle.jpg* image produces the following text results in the console:

```
Best class Index: 812
Time taken: 0.649153
Probability: 15.8467
```

4.1.8. Text detection example

This demo is used for text detection in the image using the EAST algorithm.

Demo dependencies (taken from the *opencv_extra* package):

• frozen east text detection.pb

Other demo dependencies:

imageTextN.png

Running the C++ example with the image input from the default location:

```
$: ./example_dnn_text_detection --model=frozen_east_text_detection.pb --
input=../data/imageTextN.png
```




Figure 8. Text detection graphics output

NOTE

This example accepts only the PNG image format.

Running the C++ example with the live camera input from the default location:

\$: ./example dnn text detection --model=frozen east text detection.pb

4.2. OpenCV standard machine learning demos

After deploying OpenCV on the target device, the non-neural-network demos are installed in the "rootfs" in the /usr/share/OpenCV/samples/bin/ folder. To display the results, a Yocto image with Qt 5 support is required.

4.2.1. Introduction to SVM

This example demonstrates how to create and train an SVM model using training data. When the model is trained, the labels for test data are predicted. The full description of the example is in tutorial_introduction_to_svm.

After running the demo, the graphics result is shown on the screen (Qt 5 support is required):

\$: ./example tutorial introduction to svm

Result:

1. The code opens an image and shows the training examples of both classes. The points of one class are represented with white circles and the other class uses black points.

- 2. The SVM is trained and used to classify all the pixels of the image. This results in the division of image into blue and green regions. The boundary between both regions is the optimal separating hyperplane.
- 3. Finally, the support vectors are shown using gray rings around the training examples.



Figure 9. SVM introduction graphics output

4.2.2. SVM for non-linearly separable data

This example deals with non-linearly-separable data and shows how to set the parameters of the SVM with linear kernel for these data. For more details, see SVM non linearly separable data.

After running the demo, the graphics result is shown on the screen (Qt 5 support is required):

```
$: ./example_tutorial_non_linear_svms
```

Result:

- 1. The code opens an image and shows the training data of both classes. The points of one class are represented by a light-green color and the other class is shown as light-blue points.
- 2. The SVM is trained and used to classify all pixels of the image. This divides the image into blue and green regions. The boundary between both regions is the separating hyperplane. Because the training data is non-linearly separable, some examples of both classes are misclassified; some green points lay in the blue region and some blue points lay in the green one.
- 3. The support vectors are shown with gray rings around the training examples.




Figure 10. SVM non-linearity graphics output

4.2.3. Introduction to PCA

The Principal Component Analysis (PCA) is a statistical method that extracts the most important features of a dataset. In this tutorial, it is shown how to use the PCA to calculate the orientation of an object. For more details, see the OpenCV tutorial: <u>Introduction_to_PCA</u>.


After running the demo, the graphics result is shown on the screen (Qt 5 support is required):

\$: ./example tutorial introduction to pca

Result:

The code opens an image (loaded from ../data/pca_test1.jpg), finds the orientation of the detected objects of interest, and visualizes the result by drawing the contours of the detected objects of interest, the center point, and the x-axis and y-axis regarding the extracted orientation.

NXP elQ™ Machine Learning Software Development Environment for i.MX Applications Processors, Rev. 2, 06/2019






Figure 11. PCA graphics output

4.2.4. Logistic regression

In this example, logistic regression is used to predict two characters (0 or 1) from an image. Every image matrix is reshaped from its original size of 28 x 28 to 1 x 784. A logistic regression model is created and trained on 20 images. After the training, the model can predict the labels of test images. The source code is at this link and can be run using the below command.

Demo dependencies (preparing the train data files):

```
$: wget raw.githubusercontent.com/opencv/opencv/4.0.1/samples/data/data01.xml
```

After running the demo, the graphics result is shown on the screen (Qt 5 support is required):

```
$: ./example cpp logistic regression
```

Result:

The training and test data and the comparison between the original and predicted labels are shown. The trained model reaches 95 % accuracy. The console text output is as follows:

```
original vs predicted:
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1, 1, 1, 1, 1, 1, 1, 1, 1, 1]
[0, 0, 0, 0, 0, 0, 0, 0, 0, 1, 1, 1, 1, 1, 1, 1, 0, 1, 1]
accuracy: 95%
saving the classifier to NewLR Trained.xml
loading a new classifier from NewLR Trained.xml
predicting the dataset using the loaded classifier...done!
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1, 1, 1, 1, 1, 1, 1, 1, 1, 1, 1]
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1, 1, 1, 1, 1, 1, 1, 0, 1, 1]
accuracy: 95%
```




Figure 12. Logistic regression graphics output

5. Arm Compute Library getting started guide

The Arm Compute Library [8] is a collection of low-level functions optimized for the Arm CPU and GPU architectures targeted at image processing, computer vision, and machine learning. It is a convenient repository of optimized functions that developers can source either individually or as a part of complex pipelines to accelerate algorithms and applications. The Arm compute library also supports NEON acceleration.

Two types of examples are described in the following sub-sections:

- Example based on the DNN models with random weights and inputs
- Example based on the AlexNet using the graph API

5.1. Running DNN with random weight and inputs

The Arm Compute Library contains examples for most common DNN architectures, such as AlexNet, MobileNet, ResNet, Inception v3, Inception v4, Squeezenet, and others.

All available examples are at this example build location:

• /usr/share/arm-compute-library/build/examples

Each model architecture can be tested using the "graph_[dnn_model]" application.

Here is an example of running the required DNN model with a random weight (run the example application without any arguments):

```
$: ./graph mobilenet v2
```

The application creates the required network model with random weights and predicts the random inputs. If all components work, the "Test passed" message is printed.

5.2. Running AlexNet using graph API

In 2012, AlexNet became famous when it won the ImageNet Large Scale Visual Recognition Challenge (ILSVRC), an annual challenge that aims to evaluate algorithms for object detection and image classification. AlexNet is made up of eight trainable layers (five convolution layers and three fully-connected layers). All the trainable layers are followed by the ReLu activation function, except for the last fully-connected layer, where the Softmax function is used.

The C++ AlexNet example implementation [9] uses the graph API in this folder:

/usr/share/arm-compute-library/build/examples

Demo dependencies:

- Download the archive file to the example location folder from: developer.arm.com//-/media/developer/technologies/Machine learning on Arm/Tutorials/Running AlexNet on Pi with Compute Library/compute library alexnet.zip?revision=c1a232fa-f328-451f-9bd6-250b83511e01
- Create new sub-folder and unzip the file:

```
$: mkdir assets alexnet
$: unzip compute library alexnet.zip -d assets alexnet
```

Set the environment variables for execution:

```
$: export LD LIBRARY PATH=/usr/share/arm-compute-library/build/examples/
$: export PATH ASSETS=/usr/share/arm-compute-library/build/examples/assets alexnet/
```

Run the example with the command-line arguments from the default location:

```
$: ./graph alexnet --data=$PATH ASSETS --image=$PATH ASSETS/go kart.ppm --
labels=$PATH ASSETS/labels.txt
```

The output of the successful classification is as follows:

```
----- Top 5 predictions -----
0.9736 - [id = 573], n03444034 go-kart
0.0118 - [id = 518], n03127747 crash helmet
0.0108 - [id = 751], n04037443 racer, race car, racing car
0.0022 - [id = 817], n04285008 sports car, sport car
0.0006 - [id = 670], n03791053 motor scooter, scooter
Test passed
```

6. TensorFlow getting started guide

TensorFlow [10] is an end-to-end open-source platform for machine learning. It has a comprehensive, flexible ecosystem of tools, libraries, and community resources that enable the researchers to push the state-of-the-art in ML and give the developers the ability to easily build and deploy ML-powered applications.

TensorFlow provides a collection of workflows [14] with intuitive, high-level APIs for both beginners and experts to create machine learning models in numerous languages. TensorFlow provides a variety of different toolkits that enable you to construct models at your preferred level of abstraction. Use the lower-level APIs to build models by defining a series of mathematical operations. Alternatively, you can use higher-level APIs to specify pre-defined architectures, such as linear regressors or neural networks.

6.1. Running benchmark application

This simple example is pre-installed by default on the prepared Yocto image with machine learning enablement. It performs simple TensorFlow benchmarking using the pre-defined model. The graph model file is not included in the target image due to its size. The benchmark binary file location is:

• /usr/bin/tensorflow-1.12.0/examples

Demo dependencies:

- Download the inception graph model:
 - \$: wget storage.googleapis.com/download.tensorflow.org/models/inception5h.zip
- Unzip the model file to the example target location:
 - \$: unzip inception5h.zip
- Run the example with command-line arguments from the default location:
 - \$: ./benchmark --graph=tensorflow_inception_graph.pb --max_num_runs=10

The benchmark application outputs lots of useful information, such as:

- Run order
- Top by computation time
- Top by memory use
- Summary by node type

For example, the summary node output of the TensorFlow benchmarking is as follows:

[Node type]	[count]	[avg ms]	[avg %]	[cdf %]	[mem KB]	[times called]
Conv2D	22	171.150	64.825%	64.825%	10077.888	22
MatMul	2	35.295	13.368%	78.194%	8.128	2
MaxPool	6	23.723	8.985%	87.179%	3562.496	6
LRN	2	18.823	7.129%	94.309%	3211.264	2
BiasAdd	24	8.475	3.210%	97.519%	0.000	24
Relu	14	3.847	1.457%	98.976%	0.000	14
Concat	3	1.303	0.494%	99.469%	2706.368	3
Const	50	0.619	0.234%	99.704%	0.000	50
AvgPool	1	0.544	0.206%	99.910%	32.512	1
Softmax	1	0.097	0.037%	99.947%	0.000	1
NoOp	1	0.082	0.031%	99.978%	0.000	1
Retval	1	0.022	0.008%	99.986%	0.000	1
_ Reshape	1	0.013	0.005%	99.991%	0.000	1
_Arg	1	0.012	0.005%	99.995%	0.000	1
Identity	1	0.012	0.005%	100.000%	0.000	1

Timings (microseconds): count=10 first=281154 curr=242529 min=240048 max=291365 avg=264068 std=19523

7. TensorFlow Lite getting started guide

TensorFlow Lite is a light-weight version of and a next step from TensorFlow. TensorFlow Lite is an open-source software library focused on running machine learning models on mobile and embedded devices (available at www.tensorflow.org/lite). It enables on-device machine learning inference with low latency and small binary size. TensorFlow Lite also supports hardware acceleration using AndroidTM OS neural network APIs.

TensorFlow Lite supports a set of core operators (both quantized and float) tuned for mobile platforms. They incorporate pre-fused activations and biases to further enhance the performance and quantized accuracy. Additionally, TensorFlow Lite also supports the use of custom operations in models.

TensorFlow Lite defines a new model file format, based on FlatBuffers [11]. FlatBuffers is an open-source, efficient, cross-platform serialization library. It is similar to protocol buffers, but the primary difference is that FlatBuffers does not need a parsing/unpacking step for a secondary representation before you can access the data, often coupled with per-object memory allocation. Also, the code footprint of FlatBuffers is an order of magnitude smaller than protocol buffers.

TensorFlow Lite has a new mobile-optimized interpreter, which has the key goal to keep apps lean and fast. The interpreter uses static graph ordering and a custom (less-dynamic) memory allocator to ensure minimal load, initialization, and execution latency.

7.1. Running benchmark application

This simple example is pre-installed by default on the prepared Yocto image with machine learning enablement. Its name is "benchmark_model". It performs simple TensorFlow Lite benchmarking using the pre-defined models. The model file is not included in the target image, because of its size. The example binary file location is:

• /usr/bin/tensorflow-lite-1.12.0/examples

Demo dependencies:

• Download the model file [13] using this command:

```
$: wget
download.tensorflow.org/models/mobilenet v1 2018 08 02/mobilenet v1 1.0 224 quant.tgz
```

• Unpack the model file:

```
$: tar -xzvf mobilenet v1 1.0 224 quant.tgz
```

• Run the example with the command-line arguments from the default location:

```
$: ./benchmark model --graph=mobilenet v1 1.0 224 quant.tflite
```

The output of a successful TensorFlow Lite benchmarking is as follows:

```
STARTING!
Num runs: [50]
Inter-run delay (seconds): [-1]
Num threads: [1]
Benchmark name: []
Output prefix: []
Warmup runs: [1]
Graph: [mobilenet v1 1.0 224 quant.tflite]
Input layers: []
Input shapes: []
Use nnapi : [0]
Loaded model mobilenet v1 1.0 224 quant.tflite
resolved reporter
Initialized session in 44.687ms
Running benchmark for 1 iterations
count=1 curr=180071
Running benchmark for 50 iterations
count=50 first=128160 curr=128079 min=127643 max=128319 avg=127944 std=138
Average inference timings in us: Warmup: 180071, Init: 44687, no stats: 127944
```

7.2. Running image classification example

This simple example classifies images of clothing, such as hats, shirts, and others. The "grace hopper" input image (see Figure 13) is used as a typical sample for the image classification. By default, a proper model file for this example is not included in the target image due to its size. It should be downloaded by the user to the target image.



Figure 13. Image classification input picture

Two different approaches for running this example are used. The simplest way is to use the pre-installed binary application with minimum subsequent steps (see Section 7.2.1, "Using pre-installed example"). The second approach is intended for users who want to create (build) a custom application using sources (see Section 7.2.2, "Building example from sources").

7.2.1. Using pre-installed example

The example is pre-installed by default in the prepared Yocto image with the machine-learning enablement. Its name is "label image". The example binary file location is:

/usr/bin/tensorflow-lite-1.12.0/examples

Demo dependencies:

• Download the TensorFlow model file to the example folder. It can be the model file used by the previous benchmark example (see Section 7.1, "Running benchmark application"):

```
$ wget
http://download.tensorflow.org/models/mobilenet v1 2018 08 02/mobilenet v1 1.0 224 quan
```

• Unpack the model file to the example binary location:

```
$: tar -xzvf mobilenet v1 1.0 224 quant.tgz
```

Run the example with the command-line arguments from the default location:

```
$: ./label image -m mobilenet v1 1.0 224 quant.tflite -t 1 -i grace hopper.bmp -1
labels.txt
```

NXP elQ™ Machine Learning Software Development Environment for i.MX Applications Processors, Rev. 2, 06/2019

The output of a successful classification for the "grace_hopper" input image (see Figure 13) is as follows:

```
Loaded model mobilenet v1 1.0 224 quant.tflite
resolved reporter
invoked
average time: 330.473 ms
0.780392: 653 military uniform
0.105882: 907 Windsor tie
0.0156863: 458 bow tie
0.0117647: 466 bulletproof vest
0.00784314: 835 suit
```

7.2.2. Building example from sources

The image classification example can be downloaded from the TensorFlow repository^[14] and built from these sources on the target image.

Demo dependencies:

Download and make the TensorFlow sources:

```
$ git clone https://github.com/tensorflow/tensorflow.git
$ cd tensorflow
$ git checkout r1.12
$ ./tensorflow/contrib/lite/tools/make/download dependencies.sh
$ make -f tensorflow/contrib/lite/tools/make/Makefile
$ cd tensorflow/contrib/lite/examples/label image
```

Build the "label_image" example using the GNU C++ compiler:

```
$ g++ --std=c++11 -03 bitmap helpers.cc label image.cc -I ../../.. -I
../../tools/make/downloads/flatbuffers/include -L
../../tools/make/gen/linux aarch64/lib -ltensorflow-lite -lpthread -ldl -o label image
```

• Download the TensorFlow model file to the current directory. It is the model file used by the pre-installed example (see Section 7.2.1, "Using pre-installed example"):

```
$ wget
http://download.tensorflow.org/models/mobilenet v1 2018 08 02/mobilenet v1 1.0 224 quan
t.taz
```

• Unpack the model file to the current directory:

```
$ tar -xzvf mobilenet v1 1.0 224 quant.tgz
```

• Run the example with the command-line arguments from the default location:

```
$ ./label image -m mobilenet v1 1.0 224 quant.tflite -t 1 -i testdata/grace hopper.bmp
-l ../../java/ovic/src/testdata/labels.txt
```

The output of a successful classification for the "grace_hopper" input image (see Figure 13) is the same as for the pre-installed application (see Section 7.2.1, "Using pre-installed example"):

```
Loaded model mobilenet v1 1.0 224 quant.tflite
resolved reporter
invoked
average time: 229.14 ms
0.780392: 653 military uniform
0.105882: 907 Windsor tie
0.0156863: 458 bow tie
0.0117647: 466 bulletproof vest
0.00784314: 835 suit
```

8. Arm NN getting started guide

Arm NN is an open-source inference engine framework developed by Arm and supporting a wide range of neural-network model formats, such as Caffe, TensorFlow, TensorFlow Lite, and ONNX. For i.MX 8, Arm NN runs on the CPU with NEON and has multi-core support. Arm NN does not currently support the i.MX 8 GPUs due to the Arm NN OpenCL requirements, which are not met by i.MX 8 GPUs. For more details about Arm NN, check the <u>Arm NN SDK webpage</u>.

To build Arm NN 19.02 using the Yocto Project tools, follow the steps describes in Section 3, "Yocto installation guide". Make sure to perform the additional modifications needed for Arm NN, as described in Section 3.2.4, "Yocto configuration file modifying" (see the "Add packages" instruction).

8.1. Running Arm NN tests

The Arm NN SDK provides a set of tests, which can also be considered as demos, showing what the Arm NN does and how to use it. They load neural network models of various formats (Caffe, TensorFlow, TensorFlowLite, ONNX), run the inference on a specified input data, and output the inference result. The Arm NN tests are built by default when building the rootfs image and installed in the /usr/bin folder.

Note that the input data, model configurations, and model weights are not distributed with Arm NN. Download them separately and make sure they are available on the device before running the tests. However, the Arm NN tests do not have documentation. Moreover, the input file names are hardcoded, so you must investigate the code to find out what input file names are expected.

To get started with Arm NN, the following sections explain how to prepare the input data and how to run the Arm NN tests. All of them use well-known neural network models. With only few exceptions, such pre-trained networks are available to download from the internet. The input image files and their name, format, and content are deduced by analyzing the code. However, this was not possible for all the tests. It is recommended to prepare the data on the host and then deploy them on the i.MX 8 board, where the current Arm NN tests are run.

The following sections assume that the neural network model files are stored in a folder called *models*, and the input image files are stored in a folder called *data*. Both of them are created inside a folder called *ArmnnTests*. Create this folder structure on the larger partition using the following commands:

\$: mkdir ArmnnTests
\$: cd ArmnnTests
\$: mkdir data
\$: mkdir models

8.1.1. Caffe tests

The Arm NN 19.02 SDK provides the following set of tests for the Caffe models:

/usr/bin/CaffeAlexNet-Armnn
/usr/bin/CaffeCifar10AcrossChannels-Armnn
/usr/bin/CaffeInception_BN-Armnn
/usr/bin/CaffeMnist-Armnn
/usr/bin/CaffeResNet-Armnn
/usr/bin/CaffeVGG-Armnn
/usr/bin/CaffeYolo-Armnn

Two important limitations might require a pre-processing of the Caffe model file before running the Arm NN Caffe test. Firstly, the Arm NN tests require the batch size to be set to 1. Secondly, the Arm NN does not support all Caffe syntaxes, so some previous neural-network model files require updates to the latest Caffe syntax. How to perform these pre-processing steps is described at the Arm NN GitHub page. Note that you should install Caffe on the host. See also [16].

For example, supposing you have a Caffe model that either has the batch size different than 1 or uses another Caffe defined by files *model_name.prototxt* and *model_name.caffemodel*, create a copy of the *.prototxt file (new_model_name.prototxt), modify this file to use the new Caffe syntax, change the batch size to 1, and finally run this Python script:

```
import caffe

net = caffe.Net('model_name.prototxt', 'model_name.caffemodel', caffe.TEST)

new_net = caffe.Net('new_model_name.prototxt', 'model_name.caffemodel', caffe.TEST)

new net.save('new model name.caffemodel')
```

The following sections explain how to run each of the tests, except for

"CaffeCifar10AcrossChannels-Armnn" and "CaffeYolo-Armnn". For the first one, a publicly available pre-trained model was not found. For the second one, there is no way to deduce the exact content of the input image originally used by this test.

8.1.1.1. Caffe Alex Net-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- Download the model files from: <u>raw.githubusercontent.com/BVLC/caffe/master/models/bvlc_alexnet/deploy.prototxt</u> <u>dl.caffe.berkeleyvision.org/bvlc_alexnet.caffemodel</u>
- 2. Transform the network as explained in the introductory part of Section 8.1.1, "Caffe tests".
- 3. Rename *bvlc_alexnet.caffemodel* to *bvlc_alexnet_1.caffemodel*.
- 4. Copy the bylc alexnet 1.caffemodel file to the models folder on the device.
- 5. Find a *.jpg file that contains a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: CaffeAlexNet-Armnn --data-dir=data --model-dir=models
```

8.1.1.2. CaffeInception_BN-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- Download the model files from: <u>raw.githubusercontent.com/pertusa/InceptionBN-21K-for-Caffe/master/deploy.prototxt</u> <u>www.dlsi.ua.es/~pertusa/deep/Inception21k.caffemodel</u>
- 2. Transform the network as explained in the introductory part of Section 8.1.1, "Caffe tests".

- 3. Rename the *Inception21k.caffemodel* file to *Inception-BN-batchsize1.caffemodel*.
- 4. Copy the *Inception-BN-batchsize1.caffemodel* file to the *models* folder on the device.
- 5. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: CaffeInception BN-Armnn --data-dir=data --model-dir=models
```

8.1.1.3. CaffeMnist-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. Download the model files from: raw.githubusercontent.com/BVLC/caffe/master/examples/mnist/lenet.prototxt github.com/ARM-software/ML-examples/blob/master/armnnmnist/model/lenet iter 9000.caffemodel
- 2. Transform the network as explained in the introductory part of Section 8.1.1, "Caffe tests".
- 3. Download these two archives and unpack them: yann.lecun.com/exdb/mnist/t10k-images-idx3-ubyte.gz yann.lecun.com/exdb/mnist/t10k-labels-idx1-ubyte.gz
- 4. Copy the *lenet iter 9000.caffemodel* file to the *models* folder on the device.
- 5. Copy the t10k-images.idx3-ubyte and t10k-labels.idx1-ubyte files to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: CaffeMnist-Armnn --data-dir=data --model-dir=models
```

8.1.1.4. CaffeResNet-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. Download the model file for ResNet50 from: onedrive.live.com/?authkey=%21AAFW2-FVoxeVRck&cid=4006CBB8476FF777&id=4006CBB8476FF777%2117895&parId=4006CBB 8476FF777%2117887&o=OneUp
- 2. Rename the *RestNet-50-model.caffemodel* file to *ResNet_50_ilsvrc15_model.caffemodel*.
- 3. Copy the ResNet_50_ilsvrc15_model.caffemodel file to the models folder on the device.
- 4. Download this image file and copy it to the *data* folder on the device: raw.githubusercontent.com/ameroyer/PIC/d136e9ceded0ceb700898725405d8eb7bd273bbe/val_s amples/ILSVRC2012_val_00000018.JPEG

Arm NN getting started guide

- 5. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: CaffeResNet-Armnn --data-dir=data --model-dir=models
```

8.1.1.5. CaffeVGG-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- Download the model files for VGG19 from: <u>www.robots.ox.ac.uk/~vgg/software/very_deep/caffe/VGG_ILSVRC_19_layers.caffemodel</u> <u>gist.githubusercontent.com/ksimonyan/3785162f95cd2d5fee77/raw/f02f8769e64494bcd3d7e97d</u> 5d747ac275825721/VGG_ILSVRC_19_layers_deploy.prototxt
- 2. Transform the network as explained in the introductory part of Section 8.1.1, "Caffe tests".
- 3. Rename the VGG_ILSVRC_19_layers.caffemodel file to VGG_CNN_S.caffemodel.
- 4. Copy the VGG_CNN_S.caffemodel file to the models folder on the device.
- 5. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: CaffeVGG-Armnn --data-dir=data --model-dir=models
```

8.1.2. TensorFlow tests

The Arm NN 19.02 SDK provides the following set of tests for the TensorFlow models:

```
/usr/bin/TfCifar10-Armnn
/usr/bin/TfInceptionV3-Armnn
/usr/bin/TfMnist-Armnn
/usr/bin/TfMobileNet-Armnn
/usr/bin/TfResNext-Armnn
```

Before running the tests, the TensorFlow models must be prepared for inference. This process is TensorFlow-specific and uses TensorFlow tools. Therefore, TensorFlow must be installed on your host machine.

The following sections explain how to run each of the tests, except for "TfResNext-Armnn" and "TfCifar10-Armnn", for which the publicly available pre-trained models were not found.

8.1.2.1. TfInceptionV3-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

1. From your host machine, generate the graph definition for the Inception model:

```
# model preparation
$: mkdir checkpoints
```

```
# clone the models repository
$: git clone https://github.com/tensorflow/models.git
$: cd models/research/slim/
# export the inference graph
$: python export_inference_graph.py --model_name=inception_v3 --
output file=../../../checkpoints/inception_v3 inf graph.pb
```

2. From your host machine, download the pre-trained model and use the TensorFlow tools to prepare it for inference. Note that *<path_to_tensorflow_repo>* refers to the path where you cloned or downloaded the TensorFlow repo.

```
$: cd ../../checkpoints
# download and extract the checkpoint
$: wget http://download.tensorflow.org/models/inception_v3_2016_08_28.tar.gz -q0- | tar
-xvz
# freeze the model
$: python <path_to_tensorflow_repo>/tensorflow/python/tools/freeze_graph.py --
input_graph=inception_v3_inf_graph.pb --input_checkpoint=inception_v3.ckpt --
input_binary=true --output_graph=inception_v3_2016_08_28_frozen.pb --
output node names=InceptionV3/Predictions/Reshape 1
```

- 3. Copy the *inception_v3_2016_08_28_frozen.pb* file to the *models* folder on the device.
- 4. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 5. Find a *.jpg file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.
- 6. Find a *.jpg file containing a cat. Rename it to Cat.jpg and copy it to the data folder on the device.
- 7. Run the test:

```
$: cd ArmnnTests
$: TfInceptionV3-Armnn --data-dir=data --model-dir=models
```

8.1.2.2. TfMnist-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. Download the model file from:
 - $\underline{raw.githubusercontent.com/ARM-software/ML-examples/master/armnn-mnist/model/simple_mnist_tf.prototxt$
- 2. Copy the *simple_mnist_tf.prototxt* file to the *models* folder on the device.
- 3. Download these two archives and unpack them: <u>yann.lecun.com/exdb/mnist/t10k-images-idx3-ubyte.gz</u>

yann.lecun.com/exdb/mnist/t10k-labels-idx1-ubyte.gz

- 4. Copy the *t10k-images.idx3-ubyte* and *t10k-labels.idx1-ubyte* files to the *data* folder on the
- 5. Run the test:

device.

```
$: cd ArmnnTests
$: TfMnist-Armnn --data-dir=data --model-dir=models
```

8.1.2.3. TfMobileNet-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- From your host machine, download and unpack the model file: <u>download.tensorflow.org/models/mobilenet_v1_2018_08_02/mobilenet_v1_1.0_224.tgz</u>
- 2. Copy the *mobilenet_v1_1.0_224_frozen.pb* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to *shark.jpg* and copy it to the *data* folder on the device.
- 4. Find a *.jpg file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.
- 5. Find a *.jpg file containing a cat. Rename it to Cat.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: TfMobileNet-Armnn --data-dir=data --model-dir=models
```

8.1.3. TensorFlow Lite tests

The Arm NN 19.02 SDK provides the following test for the TensorFlow Lite models:

```
/usr/bin/TfLiteInceptionV3Quantized-Armnn
/usr/bin/TfLiteInceptionV4Quantized-Armnn
/usr/bin/TfLiteMnasNet-Armnn
/usr/bin/TfLiteMobileNetSsd-Armnn
/usr/bin/TfLiteMobilenetQuantized-Armnn
/usr/bin/TfLiteMobilenetV2Quantized-Armnn
/usr/bin/TfLiteResNetV2-Armnn
/usr/bin/TfLiteVGG16Quantized-Armnn
```

The following sections explain how to run some of the tests. Some of the tests are excluded, because it was not possible to find a publicly available model or they need more resources than available on the i.MX 8 embedded application processors.

8.1.3.1. TfLiteInceptionV3Quantized-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. From your host machine, download and unpack the model file: download.tensorflow.org/models/tflite_11_05_08/inception_v3_quant.tgz
- 2. Copy the *inception_v3_quant.tflite* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 4. Find a *.jpg file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.

- 5. Find a *.jpg file containing a cat. Rename it to Cat.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: TfLiteInceptionV3Quantized-Armnn --data-dir=data --model-dir=models
```

8.1.3.2. TfLiteMnasNet-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. From your host machine, download and unpack the model file: download.tensorflow.org/models/tflite/mnasnet 1.3 224 09 07 2018.tgz
- 2. Copy the *mnasnet_1.3_224/mnasnet_1.3_224.tflite* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 4. Find a *.*jpg* file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.
- 5. Find a *.jpg file containing a cat. Rename it to Cat.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: TfLiteMnasNet-Armnn --data-dir=data --model-dir=models
```

8.1.3.3. TfLiteMobilenetQuantized-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- From your host machine, download the model file:

 <u>http://download.tensorflow.org/models/mobilenet_v1_2018_08_02/mobilenet_v1_1.0_224_quan_t.tgz</u>
- 2. Copy the *mobilenet_v1_1.0_224_quant.tflite* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 4. Find a *.jpg file containing a dog. Rename it to Dog.jpg and copy it to the data folder on the device.
- 5. Find a *.jpg file containing a cat. Rename it to Cat.jpg and copy it to the data folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: TfLiteMobilenetQuantized-Armnn --data-dir=data --model-dir=models
```

8.1.3.4. TfLiteMobilenetV2Quantized-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. From your host machine, download the model file:

 download.tensorflow.org/models/tflite_11_05_08/mobilenet_v2_1.0_224_quant.tgz
- 2. Copy the *mobilenet_v2_1.0_224_quant.tflite* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to shark.jpg and copy it to the data folder on the device.
- 4. Find a *.jpg file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.
- 5. Find a *.*jpg* file containing a cat. Rename it to *Cat.jpg* and copy it to the *data* folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: TfLiteMobilenetV2Quantized-Armnn --data-dir=data --model-dir=models
```

8.1.4. ONNX tests

The Arm NN provides the following set of tests for ONNX models:

```
/usr/bin/OnnxMnist-Armnn
/usr/bin/OnnxMobileNet-Armnn
```

The following sections explain how to run each of the tests.

8.1.4.1. OnnxMnist-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- From your host machine, download and unpack the model file: <u>onnxzoo.blob.core.windows.net/models/opset_8/mnist/mnist.tar.gz</u>
- 2. Rename the *model.onnx* file to *mnist_onnx.onnx* and copy it to the *models* folder on the device.
- 3. Download the following two archives and unpack them (after unpacking, rename the files to use dots instead of hyphens: t10k-images.idx3-ubyte and t10k-labels.idx1-ubyte, respectively): yann.lecun.com/exdb/mnist/t10k-images-idx3-ubyte.gz
 yann.lecun.com/exdb/mnist/t10k-labels-idx1-ubyte.gz
- 4. Copy the *t10k-images.idx3-ubyte* and *t10k-labels.idx1-ubyte* files to the *data* folder on the device.
- 5. Run the test:

```
$: cd ArmnnTests
$: OnnxMnist-Armnn --data-dir=data --model-dir=models
```

8.1.4.2. OnnxMobileNet-Armnn

To run this test using the folder structure described in the introductory part, perform these steps:

- 1. From your host machine, download and unpack the model file: s3.amazonaws.com/onnx-model-zoo/mobilenet/mobilenetv2-1.0/mobilenetv2-1.0.tar.gz
- 2. Copy the unpacked *mobilenetv2-1.0.onnx* file to the *models* folder on the device.
- 3. Find a *.jpg file containing a shark. Rename it to *shark.jpg* and copy it to the *data* folder on the device.
- 4. Find a *.jpg file containing a dog. Rename it to *Dog.jpg* and copy it to the *data* folder on the device.
- 5. Find a *.*jpg* file containing a cat. Rename it to *Cat.jpg* and copy it to the *data* folder on the device.
- 6. Run the test:

```
$: cd ArmnnTests
$: OnnxMobileNet-Armnn --data-dir=data --model-dir=models -i 3
```

8.2. Using Arm NN in a custom C/C++ application

You can create your own C/C++ applications for the i.MX 8 family of devices using Arm NN capabilities. This requires writing the code using the Arm NN API, setting up the build dependencies, building the code, and deploying your application. Below is a detailed description for each of these steps. Note that the scenario is cross-compiling a C/C++ application on a Linux OS machine for an i.MX 8 family device board.

1. Write the code.

A good starting point to understand how to use Arm NN API in your own application is the <u>armnn-mnist example</u> provided by Arm. It includes two applications; one shows how to load and run inference for a MNIST TensorFlow model, and the second one shows how to load and run inference for a MNSIT Caffe model. See the Arm tutorial <u>Deploying a TensorFlow MNIST</u> model on Arm NN.

2. Set up the build dependencies.

From a software developer's perspective, Arm NN is a library. Therefore, create and build an application which uses the Arm NN features, set of Arm NN headers, and set of Arm NN libraries for the target device. The Arm NN headers and libraries are all available within the SDK. Build the SDK when building the Yocto image and install it on your local machine, as described in Section 3.2, "Building NXP eIQ software support using Yocto Project tools". When this is done, find:

- Arm NN headers in:
 - <Yocto_SDK_install_folder>/sysroots/aarch64-poky-linux/usr/include
- Arm NN libraries in:
 - <Yocto_SDK_install_folder>/sysroots/aarch64-poky-linux/usr/lib

3. Build the code.

To build the "armnn-mnist" example provided by Arm, use the Makefile included in the project with a few minor changes:

- Remove the definition of "ARMNN_INC" and all its uses. The Arm NN headers are already available in the default include directories.
- Remove the definition of "ARMNN_LIB" and all its uses. The Arm NN libraries are already available in the default linker search path.
- Replace "g++" by "\${CXX}".

Build the example:

- Source the SDK environment:

```
$: source <Yocto SDK install folder>/environment-setup-aarch64-poky-linux
```

– Run make:

\$: make

4. Deploy the applications.

At this point, you have two binaries ready to be deployed on the i.MX 8 family device board. All you need to take care of are the runtime dependencies. Regarding the input data, these dependencies are described at the "armnn-mnist" example page. The suggested image described in this document requires Arm NN library dependencies already available on the board and you can run your Arm NN application on the i.MX 8 family device board.

9. ONNX Runtime getting started guide

ONNX Runtime is an open-source inference engine framework developed by Microsoft, supporting the ONNX model format. ONNX Runtime runs on the CPU with NEON and has multi-core support. ONNX Runtime does not currently support the i.MX 8 GPUs due to the lack of OpenCL support. For more details about ONNX Runtime, see the official ONNX Runtime project webpage.

To build Yocto with ONNX Runtime, follow the steps described in Section 3, "Yocto installation guide". Make sure to perform the additional modifications needed for ONNX Runtime, as described in Section 3.2.4, "Yocto configuration file modifying" (see the "Add packages" part).

9.1. Running ONNX Runtime test

ONNX Runtime provides a tool that runs a collection of standard tests provided in the ONNX model Zoo. The tool named "onnx_test_runner" is installed in the /usr/bin folder.

The ONNX tests are available at <u>github.com/onnx/models</u> and consist of various models in the ONNX format with associated input and expected output data.

Here is an example with the steps required to run the "squeezenet" test:

 Download and unpack the latest release of the "squeezenet" test archive: <u>github.com/onnx/models/tree/master/squeezenet</u> <u>s3.amazonaws.com/download.onnx/models/opset</u> 8/squeezenet.tar.gz

- 2. Copy the *squeezenet* folder containing the model and test data on the device; for example, to the /home/root folder.
- 3. Run the "onnx test runner" tool, providing the *squeezenet* folder path as the command-line parameter:

```
$: ls /home/root/squeezenet/
model.onnx
           test data set 11 test data set 5 test data set 9
test_data_set_0 test_data_set_2 test_data_set_6
test data set 1 test data set 3 test data set 7
test data set 10 test data set 4 test data set 8
$: onnx_test_runner /home/root/squeezenet/
result:
       Models: 1
       Total test cases: 12
               Succeeded: 12
               Not implemented: 0
               Failed: 0
       Stats by Operator type:
               Not implemented(0):
               Failed:
Failed Test Cases:
$:
```

10. References

- 1. NXP eIQ Software
- 2. NXP eIQ Software Support Community
- 3. i.MX8 family of Application processor fact sheet:
- 4. i.MX Software and development tools
- 5. L4.14.98 2.0.0 LINUX DOCS documentation
- 6. Deep learning in OpenCV
- 7. OpenCV Change Logs
- 8. ARM Compute library
- 9. Running Alexnet on Rapsberry PI with Compute Library
- 10. TensorFlow
- 11. FlatBuffers
- 12. What is the difference between TensorFlow and TensorFlow lite
- 13. TensorFlow Hosted Models
- 14. TensorFlow sources
- 15. https://searchenterpriseai.techtarget.com/definition/machine-learning-ML
- 16. Arm NN documentation for caffe support

35

11. Revision history

Table summarizes the changes done to this document since the initial release.

Table 1. Revision history

Revision number	Date	Substantive changes
0	05/2019	Initial release.
1	06/2019	Updated Section 7.2, "Running image classification example".
2	06/2019	Minor formatting changes.

How to Reach Us:

Home Page: www.nxp.com

Web Support:

www.nxp.com/support

Information in this document is provided solely to enable system and software implementers to use NXP products. There are no express or implied copyright licenses granted hereunder to design or fabricate any integrated circuits based on the information in this document. NXP reserves the right to make changes without further notice to any products herein.

NXP makes no warranty, representation, or guarantee regarding the suitability of its products for any particular purpose, nor does NXP assume any liability arising out of the application or use of any product or circuit, and specifically disclaims any and all liability, including without limitation consequential or incidental damages. "Typical" parameters that may be provided in NXP data sheets and/or specifications can and do vary in different applications, and actual performance may vary over time. All operating parameters, including "typicals," must be validated for each customer application by customer's technical experts. NXP does not convey any license under its patent rights nor the rights of others. NXP sells products pursuant to standard terms and conditions of sale, which can be found at the following address: www.nxp.com/SalesTermsandConditions.

While NXP has implemented advanced security features, all products may be subject to unidentified vulnerabilities. Customers are responsible for the design and operation of their applications and products to reduce the effect of these vulnerabilities on customer's applications and products, and NXP accepts no liability for any vulnerability that is discovered. Customers should implement appropriate design and operating safeguards to minimize the risks associated with their applications and products.

NXP, the NXP logo, NXP SECURE CONNECTIONS FOR A SMARTER WORLD, COOLFLUX, EMBRACE, GREENCHIP, HITAG, I2C BUS, ICODE, JCOP, LIFE VIBES, MIFARE, MIFARE CLASSIC, MIFARE DESFIRE, MIFARE PLUS, MIFARE FLEX, MANTIS, MIFARE ULTRALIGHT, MIFARE4MOBILE, MIGLO, NTAG, ROADLINK, SMARTLX, SMARTMX, STARPLUG, TOPFET, TRENCHMOS, UCODE, Freescale, the Freescale logo, AltiVec, C-5, CodeTEST, CodeWarrior, ColdFire, ColdFire+, C-Ware, the Energy Efficient Solutions logo, Kinetis, Layerscape, MagniV, mobileGT, PEG, PowerQUICC, Processor Expert, QorlQ, QorlQ Qonverge, Ready Play, SafeAssure, the SafeAssure logo, StarCore, Symphony, VortiQa, Vybrid, Airfast, BeeKit, BeeStack, CoreNet, Flexis, MXC, Platform in a Package, QUICC Engine, SMARTMOS, Tower, TurboLink, and UMEMS are trademarks of NXP B.V. All other product or service names are the property of their respective owners. AMBA, Arm, Arm7, Arm7TDMI, Arm9, Arm11, Artisan, big.LITTLE, Cordio, CoreLink, CoreSight, Cortex, DesignStart, DynamlQ, Jazelle, Keil, Mali, Mbed, Mbed Enabled, NEON, POP, RealView, SecurCore, Socrates, Thumb, TrustZone, ULINK, ULINK2, ULINK-ME, ULINK-PLUS, ULINKpro, µVision, Versatile are trademarks or registered trademarks of Arm Limited (or its subsidiaries) in the US and/or elsewhere. The related technology may be protected by any or all of patents, copyrights, designs and trade secrets. All rights reserved. Oracle and Java are registered trademarks of Oracle and/or its affiliates. The Power Architecture and Power.org word marks and the Power and Power.org logos and related marks are trademarks and service marks licensed by Power.org.

© 2019 NXP B.V.

Document Number: UM11226

Rev. 2 06/2019

